cecris

Public

Notifications · Fork 0 · Star 0

main · Go to file · Code

zorel Add graceful SIGTERM/... 9b444e7 · 3 days ago

src	Add graceful SIGTERM/...	3 days ago
tests	Add graceful SIGTERM/...	3 days ago
web	Add graceful SIGTERM/...	3 days ago
.gitignore	cecris-0.1.0: real-time ...	3 days ago
Cargo.lock	cecris-0.1.0: real-time ...	3 days ago
Cargo.toml	Apache-2.0 license	3 days ago
LICENSE	Apache-2.0 license	3 days ago
Makefile	Add graceful SIGTERM/...	3 days ago
README.md	Add graceful SIGTERM/...	3 days ago

README · Apache-2.0 license

cecris — web edition

Server-authoritative, real-time multiplayer falling-block battle. Rust server with an event-driven core and a browser client, talking a compact binary protocol over WebSocket — with SSE + POST fallback.

Rooms are addressed by game id, so a single link (`/g/<id>`) is all a group needs. Any number of rooms run in parallel on the same process.

Listen address and port are command-line options; environment variables provide the defaults when a flag is omitted:

option	env	default	meaning
`-b, --bind <ADDR>`	`BIND`	`0.0.0.0`	listen address
`-p, --port <PORT>`	`PORT`	`8000`	TCP listen port

```
./target/release/cecris --bind 127.0.0.1 --port 1
./target/release/cecris --port=9001
./target/release/cecris --help
```

Open the site, pick a nickname and a game code, then share the room link. The first player in a room is the host, controls the round options, and can start once at least two players are connected and everyone has pressed **Ready**. Two to six players per room; late joiners enter the next round.

Controls

key	action
← / → (A / D)	move, with DAS/auto-repeat
↑ or X	rotate clockwise
Z	rotate counter-clockwise
↓ (S)	soft drop
Space	hard drop
1–5	select a special from inventory
click a field	use the selected special on that field (own included)
Esc	cancel special selection
Enter (chat box)	send chat

The own board is client-predicted for horizontal moves and rotations; the server reconciles at 20+ Hz. Opponent boards and all rule changes are server-authoritative.

Rules

A 12 × 22 field with seven piece shapes and classic rotation tables. Pieces are dealt from a per-player 7-bag; all seven shapes are shuffled, dealt once each, then the bag is reshuffled. This limits droughts and long runs of the same shape compared with picking each piece independently.

A **special block** is a lettered block embedded in a stack. Clearing a row that contains one adds it to your **inventory**, the list beside your board. Select an inventory entry and click a field to spend it there; useful specials can be used on your own field. The inventory starts empty and holds at most five collected specials.

The host edits the room's options in the lobby; every joiner sees the same values read-only and the settings carry over between rounds. Editing locks when the countdown starts. The options panel is collapsed by default; guests only see it when at least one option differs from the defaults.

Every connected player must press **Ready**. The host can start only when everyone, including the host, is ready. Starting runs a 3-second countdown; joining or leaving in a way that breaks the ready set cancels it back to the lobby. Readiness resets after each round. The lobby also shows a short how-to-play card.

option	default	range
Start level	1	1–15
Starting garbage rows	0	0–12
Lines per level	10	1–50
Level step per threshold	1	1–5
Special block every … lines	5	0–50 (0 disables field specials)
Specials per trigger	1	0–5
Inventory capacity	5	1–8
Garbage on 2/3/4-line clears	on	on / off

What the options mean

- **Start level** — the level and falling speed applied to the first piece. It changes speed and the level display only; it does not add blocks. Higher is faster.
- **Starting garbage rows** — rows of mixed blocks, each with one gap, placed at the bottom of every player's field before the first piece. `0` starts with an empty field; more rows leave less room from the beginning.
- **Lines per level** — how many cleared lines a player must accumulate to gain a level. Lower values ramp the falling speed up sooner.
- **Level step per threshold** — how many levels are gained each time that threshold is reached. `1` is the normal ramp; higher values make each threshold much faster.
- **Special block every N lines** — after every N cumulative cleared lines, the game injects special blocks into that player's stacks by replacing normal blocks. `0` disables injection. The counter is per-player: clearing 6 lines with `N = 5` triggers once and leaves 1 line toward the next trigger.
- **Specials per trigger** — how many special blocks are injected each time that cadence fires. With the default `1`, one block appears every 5 lines. `0` means the cadence is consumed but nothing is placed.
- **Inventory capacity** — the maximum number of collected special blocks you can hold at once. When the inventory is full, further collected specials are discarded. Every stored entry can be spent once.
- **Garbage on 2/3/4-line clears** — when on, clearing 2, 3, or 4 rows at once also pushes 1, 2, or 4 rows of garbage onto every other living player. When off, only special blocks send garbage.

Round flow

- Clearing a full row removes it and collapses the rows above. Clearing several rows at once is worth more pressure when garbage attacks are on.
- Clear rows containing special blocks to collect them; clearing several such rows collects every special in them, up to the inventory capacity.
- A player is out when a new piece cannot enter the field, or when garbage pushes a row above the top.
- The last player still able to place pieces wins. Seven seconds after the round, the room returns to the lobby with the same options.
- A player dropped mid-round keeps their slot and board for 3 minutes and can reconnect with the same browser tab token; the board is frozen while disconnected. Tokens are tab-scoped (`sessionStorage`), so two tabs in one browser join as two different players, while reloading a tab keeps its player identity.

Specials:

id	glyph	name	effect
0	A	Add Line	pushes one garbage line onto the target
1	C	Clear Line	shifts the target's field down and clears the top row
2	N	Nuke Field	empties the target's field
3	R	Clear Random	removes 10 random cells from the target
4	S	Switch Fields	swaps your field with the target's
5	B	Clear Specials	turns the target's special blocks into normal blocks
6	G	Block Gravity	compacts all columns downward on the target
7	Q	Blockquake	shifts every row horizontally by a random amount
8	O	Block Bomb	removes all bomb blocks and scatters their neighbours

No teams, separate spectator connections, MIDI soundtrack, or shared-piece-sequence variant. Six block colours are used instead of five so each piece has its own hue.

Protocol

Binary frames, first byte = message type. WebSocket frames are binary and unmasked server → client. The SSE fallback carries the same bytes base64-encoded in `event: bin` messages; client → server fallback uses `POST /api/input?id=…` with the raw frame as the body.

Client → server:

type	payload
`0x01` MOVE	`dx` action (0 left, 1 right, 2 rotate CW, 3 rotate CCW, 4 soft drop, 5 hard drop)
`0x02` SPECIAL	`u8` special, `u8` target slot (1–6)
`0x03` START	— (host only, ≥2 connected, everyone ready, lobby phase)
`0x04` CHAT	UTF-8 text (≤240 chars)
`0x05` PING	8-byte nonce, echoed by the server
`0x06` LEAVE	—
`0x07` RESYNC	— (server replies with a snapshot)
`0x08` OPTIONS	8× `u8` : start level, garbage rows, lines/level, level step, special every, special count, inventory cap, attacks (0/1) — host only, lobby only
`0x09` READY	`u8` 0/1 — lobby only

Server → client:

type	payload
`0x84` LOBBY	JSON: phase, host, winner, countdown ms, options, player list
`0x85` STATE	`u32` tick, then 6 slot records
`0x82` BOARD	`u8` slot , `u32` version , 132 packed bytes
`0x83` EVENT	JSON: chat, line clears, attacks, special use, top-out, round over, errors
`0x86` SNAPSHOT	`u32` tick, then 6 × `u8` slot + `u32` version , 132 packed bytes
`0x81` PONG	echoed nonce
`0x80` HELLO	JSON: your slot, reconnect token, game id

`STATE` slot record (only when present):

```
u8 present | u8 alive | u8 level | u16 lines | u16 score |
i8 x | i8 y | u8 rot | u8 next | u8 n | n × u8 hq
```

Board bytes pack two cells per byte, high nibble first. Cell values: 0 empty, 1–6 block colour, 7–15 special (`kind + 6` = `special id`). Boards are only broadcast when their version changes; `STATE` (~20–100 bytes) goes out at 22 Hz. Clients can request a snapshot after a tab wake-up or a missed frame.

Lobby JSON example:

```
{"game":"frisgo","phase":"lobby","host":1,"winner":0,"countdown":0,
 "options":{"initialLevel":1,"startingLines":0,
            "specialEvery":5,"specialCount":1,"in
 "players":[{"id":1,"nick":"anne","wins":2,"conn
```

`phase` ∈ `lobby` , `countdown` , `playing` , `over` . `id` is the countdown remaining in milliseconds, `ready` is the player's ready-readiness. `inGame` distinguishes players in the current round from players waiting for the next one.

Transports

1. **WebSocket** — `GET /api/ws?gc=&nick=&token=`. — primary, lowest latency.
2. SSE — `GET /api/sse?gc=&nick=&token=`. (server → client) plus `POST /api/input?id=…` (client → server). The stream starts with `event: hello` carrying the session id, then `event: bin` baseN frames.
3. Force the fallback with `./gc/ch/transport=sse` ; the client otherwise tries WebSocket first and drops to SSE on failure, with exponential reconnect backoff.

`GET /api/status` is a small, uncached JSON probe:

```
{"maintenance":false,"activeGames":1}
```

The landing page polls it every 2 seconds to show how many rounds are in progress and whether the server is in maintenance.

All sockets are `TCP_NODELAY` ; state application is immediate and the rule engine runs on a 10 ms tick with 45 ms state broadcasts. Moves are applied on arrival, so input latency is one network RTT, not one tick.

Shutdown and maintenance

Sending `SIGTERM` (`kill -15`) puts the server into maintenance mode:

- Existing rounds keep running and streaming.
- Pending countdowns are cancelled; new connections, joins, and round starts are rejected with a maintenance message.
- The process exits with status 0 once no game with connected players remains.
- If no game is active at signal time, it exits immediately.

The landing page shows the maintenance state and the running-game count; invite links opened during maintenance show a "New games paused" overlay.

About

Real-time multiplayer falling-block battle: zero-dependency Rust server with WebSocket + SSE browser client.

game multiplayer rust sse websocket

Readme · Apache-2.0 license · Activity · 0 stars · 0 watching · 0 forks · Report repository

Releases 1

cecris 0.1.0 — Latest — 3 days ago

Contributors 1

zorel Aurélien DESMY

Languages

Rust 54.2% · JavaScript 37.9% · CSS 7.1% · Other 0.7%

Architecture

```
src/main.rs      listener, ticker thread
src/server.rs    routes, WebSocket + SSE + POST h
src/state.rs     Arc<Mutex<State>>, tick, snapsho
src/game.rs      board, pieces, gravity, line cle
src/proto.rs     frame encoding/decoding and pack
src/http.rs      tiny HTTP/1.1 request parser and
src/ws.rs        WebSocket handshake, frame reade
src/shutdown.rs  SIGTERM flag and maintenance mod
src/util.rs      SHA-1, base64, query parsing, ua
static/          index.html, app.js, style.css
tests/e2e.mjs    protocol integration test (node
tests/maintenance.mjs  SIGTERM/maintenance integ
```

The server is server-authoritative: clients send inputs, never board states. Each room holds at most six player slots; the game state is mutated under one room mutex, which also serialises broadcasts. Rooms live in a `HashMap` and are dropped when empty (35 s in the lobby, 3 minutes mid-round to allow reconnects).

There are no third-party crates: HTTP, WebSocket framing (including masking and fragmentation), SHA-1/base64 for the handshake, and all game logic are in-tree.

Testing

```
make test              # rules, specials, protocol, 
make e2e               # release build, starts a se
make maintenance       # SIGTERM: wait for games, r
make check             # all of the above
```

`make run` serves on the fixed address `127.0.0.1:8099`. For any other address run the binary directly with its flags. The equivalent manual e2e run:

```
cargo build --release
./target/release/cerclo --bind 127.0.0.1 --port 
BASE=http://127.0.0.1:8099 node tests/e2e.mjs
```

The e2e test drives two WebSocket clients through a full round to top-out, verifies state-frame rate, chat, board diffs, readiness gating and the 3-second countdown, host-edited options visible to a joiner and applied to the next round, an SSE player (including POST/bad inputs and readiness), a parallel second room, and reconnect with token into a running game.

The maintenance test spawns its own server and verifies both shutdown paths: immediate exit when idle, and a running game that stays up, rejects new games with a maintenance message, keeps streaming to existing players, then exits after the round ends.

Deployment

Run the binary behind a TLS-terminating reverse proxy; the client selects `ws://` or `wss://` from `location.protocol`, and SSE needs buffering disabled:

```
example.com {
    reverse_proxy 127.0.0.1:8080
    flush_interval -1
}
```

SSE responses deliberately omit `Connection` and `Content-Length` and send `X-Accel-Buffering: no` with chunked transfer encoding. That combination is what keeps event streams flowing through Cloudflare Tunnel and nginx; do not re-add those headers in a proxy.

```
location /api/sse {
    proxy_pass http://127.0.0.1:8080;
    proxy_buffering off;
    proxy_cache off;
    proxy_read_timeout 1h;
}
location /api/ws {
    proxy_pass http://127.0.0.1:8080;
    proxy_read_timeout 1h;
    proxy_http_version 1.1;
    proxy_set_header Upgrade $http_upgrade;
    proxy_set_header Connection "upgrade";
}
```

Static HTML, JS, and CSS are served with `Cache-Control: no-store`; the index links assets with a content hash (`/app.js?v=…`). After rebuilding and restarting the server, reload an already-open tab once — a tab still running an older client has no **Ready** button, so the server refuses to start its round.

There is no account system: the reconnect token in `sessionStorage` is a bearer capability for one player slot, and room ids are public.

License

Copyright 2026 Aurélien DEHAY.

Licensed under the Apache License, Version 2.0. See LICENSE for the full text.

Terms Privacy Security Status Community Docs Contact Manage cookies
Do not share my personal information
© 2026 GitHub, Inc.